



MT Software Suite 4.4 - Public release notes

New version	MT Software Suite 4.4
Previous version	MT Software Suite 4.3
Release date	July 8 th , 2015
Meaning of icons	+added, ^changed, !note, #fixed, -removed

1. Notes

This MT Software Suite is the first release version for the MTi 1-series. It is not recommended for MTi 10-series, MTi 100-series and MTw.

MT Software Suite 4.4 does not contain a Firmware Updater.

Supported platform overview

Software platform	Notes on support
Windows XP	Last support in 4.2.1
Windows 7 32-bit	Officially supported
Windows 7 64-bit	Officially supported
Windows 8 64-bit	Tested, no official support
Linux 32-bit	Officially supported
Linux 64-bit	Officially supported
Android ARMv7, Android 4.4.2 (API Level 19 and higher)	Available on request for limited devices, no official support

2. Major improvements and features

Support for MTi 1-series:

- Full MT Software Suite:
 - MT Manager
 - Xsens Device API (XDA, Windows and Linux)
 - Magnetic Field Mapper
- Examples for Cortex-M0, M0+, M3 and M4. Available on <https://developer.mbed.org/teams/Xsens/>.

Note: As this release is solely intended for use with the first release of the MTi 1-series, the Firmware Updater is not installed.

3. Bug fixes

4. Minor updates

5. Known issues

- MTi 1-series Development Board is not yet in the 14.4 LTS release of the Ubuntu Linux kernel. Add the MTi 1-series manually.
- [2841] SampleTimeFine cannot be disabled in exporter