



## MT Software Suite 4.6.3 - release notes

<b>New version</b>	<b>MT Software Suite 4.6.3;</b> <b>MTi 10/100-series FW 1.4.16;</b> <b>MTi 1-series FW 1.0.18;</b>
Previous version	MT Software Suite 4.6 MTi 10/100-series FW 1.4.12 MTi 1-series FW 1.0.16
Release date	August 10 <sup>th</sup> , 2016
Meaning of icons	+added, ^changed, !note, #fixed, -removed

### 1 Notes

+ [MTSDK-3661] AHS off by default, also for VRU\_general, can be turned on with SetOptions, also via Device Settings.

! [MTSDK-3732] This release requires that the drivers of your graphics card are up to date. When they are not, MT Manager may crash when opening graphs.

Supported platform overview:

<b>Software platform</b>	<b>Notes on support</b>
Windows XP	Last support in 4.2.1
Windows 7 32-bit	Officially supported
Windows 7 64-bit	Officially supported
Windows 8 64-bit	Tested, no official support
Windows 10 64-bit	Tested, no official support
Linux 32-bit (Ubuntu 16.04)	Officially supported
Linux 64-bit (Ubuntu 16.04)	Officially supported

## 2 Improvements and features

### 2.1 MTi improvements

^[MTSDK-3698, MTSDK-3787] Gyro Bias Estimation improved with faster convergence times (not for MTi-G-7xx).

^[MTSDK-3698] For MTi 100-series: when AHS is enabled, cZRU is enabled to be used in conjunction with AHS

+^[MTSDK-3798] Added \$XSVEL to MTi-G-710 (velocity output in ASCII).

### 2.2 MT Manager and MT SDK

+^[MTSDK-3729] Added boolean to Device Settings in MT Manager to enable AHS easier

+^[MTSDK-3689] Added licenses in .rtf format to SDK

## 3 Known issues

- [MTSDK-3345] Data in graphs are sometimes not shown when setting display preference to “as fast as possible”.
- [MTSDK-3690] ASCII-exporter sometimes results in a crash